

OPSÆTNING AF MAGICAD

INDHOLD

Installation af MagiCAD.....	1
Aktivering af MagiCAD.....	6


INSTALLATION AF MAGICAD

1. Via din webbrowser (Chrome, Internet Explorer eller andet) gå til hjemmesiden:
<https://portal.magicad.com/Download/GetProductCategoryList?categoryId=1>

Husk at vælge Autodesk Revit under Technology (som default er den sat til Autodesk AutoCAD).

Download MagiCAD

Welcome to the MagiCAD download page. To download MagiCAD installation package, define Autodesk technology and operating system, select the MagiCAD version, download site, MagiCAD product and sign in to begin download.



The screenshot shows the MagiCAD download page with the following configuration options:

- TECHNOLOGY: Autodesk Revit
- OPERATING SYSTEM: Windows 64-bit
- MAGICAD VERSION: 2021
- MAGICAD PRODUCT: MagiCAD 2021 for Revit 2021 (EXE)
- DOWNLOAD LOCATION: Europe

Below these options, it shows the date "03.06.2020" and the file size "1,1 GB". A button labeled "Sign in to download" is highlighted with a blue arrow. At the bottom, under "OTHER USEFUL TOOLS", there are links for "MagiCAD templates", "Network License Server Utilities", and "Installation instructions".

Klik på Sign in to download.

2. Angiv MagiCad activation ID:
Act-60b6c1b8-6c47-49e6-a3b4-cc2317ec57ec-0
og klik på Sign in.

Sign in
X

Please sign in using your MagiCAD activation ID. You can find it from the email we sent you upon the purchase.

MagiCAD activation ID

Close
SIGN IN

3. Efter login så ser du dette billede.

Vælg Autodesk Revit i Technology (som default den er sat til Autodesk AutoCAD).

Tryk på Download.

Download MagiCAD

Welcome to the MagiCAD download page. To download MagiCAD installation package, define Autodesk technology and operating system, select the MagiCAD version, download site, MagiCAD product and sign in to begin download.

TECHNOLOGY ⓘ
Autodesk Revit

OPERATING SYSTEM ⓘ
Windows 64-bit

MAGICAD VERSION ⓘ
2021

MAGICAD PRODUCT ⓘ
MagiCAD 2021 for Revit 2021 (EXE)

DOWNLOAD LOCATION ⓘ
Europe


03.06.2020 1,1 GB

DOWNLOAD
Reset code


OTHER USEFUL TOOLS
[MagiCAD templates](#)
[Network License Server Utilities](#)
[Installation instructions](#)

4. Download zip-filen, pak filen ud og installer (dobbeltklik på **MagiCAD 2021 for Revit 2021.exe**, der hvor du har udpakket filen). Hvordan du udpakker filer afhænger af hvilket program, du anvender til zip-filer. (alle studerende burde vide hvordan man gør).


5. Sæt hak ved begge muligheder




6. Sæt hak i Accept the terms... og klik Next



7. Klik Next




8. Klik Next



9. Klik Install




10. Klik Finish




AKTIVERING AF MAGICAD


11. Efter installation dukker Magicad mappen op i Start Menu.
Åbn License Management Utility



12. Vælg Options




13. Skriv 2800@magicad.ait.dtu.dk i Server og 2194 i License borrow port
Klik på Test connections.



The image shows a 'Network settings' dialog box. It has two sections: 'Stand Alone License Activation' and 'Network License Usage'. In the first section, 'Use MagiCAD Activation Server (recommended)' is selected. In the second section, 'Use network licenses' is checked. Below this, there are two input fields: 'Server' containing '2800@magicad.ait.dtu.dk' and 'License borrow port' containing '2194'. A 'Test connections' button is highlighted with a blue arrow. At the bottom right are 'Save' and 'Cancel' buttons.

14. Connection OK viser 4 gange, tryk på Close.



The image shows a 'Connection test' dialog box. It has a title bar with a home icon and standard window controls. The main area is titled 'Testing network settings...' and contains a green progress bar. Below the progress bar is a table with four rows, each showing a service name and its connection status.


MagiCAD Activation Server	Connection OK.
MagiCAD License Data Service	Connection OK.
Local Network License Server	Connection OK.
Local License Information Service	Connection OK.

A 'Close' button is located at the bottom right of the dialog box.

15. Tryk på Save

16. Klik på faneblad Networks Licenses

Vælg den sidste Subscription (borrowable). Herunder er en eksempel på et udlån af MagiCad licens.



17. Klik på Borrow

Vælg 30 dage frem

Licens er nu vist en dato som vist på billedet.

Klik på Exit

